



SigmaStar Camera RTC User Guide

Version 0.1



© 2020 SigmaStar Technology Corp. All rights reserved.

SigmaStar Technology makes no representations or warranties including, for example but not limited to, warranties of merchantability, fitness for a particular purpose, non-infringement of any intellectual property right or the accuracy or completeness of this document, and reserves the right to make changes without further notice to any products herein to improve reliability, function or design. No responsibility is assumed by SigmaStar Technology arising out of the application or use of any product or circuit described herein; neither does it convey any license under its patent rights, nor the rights of others.

SigmaStar is a trademark of SigmaStar Technology Corp. Other trademarks or names herein are only for identification purposes only and owned by their respective owners.



REVISION HISTORY

Revision No.	Description	Date
0.1	<ul style="list-style-type: none">Initial release	12/18/2019



TABLE OF CONTENTS

REVISION HISTORY i

TABLE OF CONTENTS..... ii

1. OVERVIEW 1

2. RTC OPERATION METHOD AND SPECIFICATION 2

2.1. Showing System Clock 2

2.2. Setting System Clock 2

2.3. Showing RTC Clock..... 2

2.4. Setting RTC Clock to System Clock..... 2



1. OVERVIEW

The RTC is implemented using standard Linux architecture; therefore, user can operate the RTC based on the standard RTC interface

2. RTC OPERATION METHOD AND SPECIFICATION

2.1. Showing System Clock

Command: date

```
/ # date
Thu Jan  1 00:00:04 UTC 1970
```

2.2. Setting System Clock

Command: date MMDDhhmmYYYY.ss

MM: month (01-12)

DD: day (01-31)

hhmm: time (0000-2359)

YYYY: year [optional]

ss: seconds (00-59) [optional]

```
/ # date 112214582015.30
Sun Nov 22 14:58:30 UTC 2015
```

2.3. Showing RTC Clock

Command: hwclock

```
/ # hwclock
Thu Jan  1 00:00:05 1970  0.000000 seconds
```

2.4. Setting RTC Clock to System Clock

Command: hwclock -w

```
/ # hwclock -w
/ # hwclock
Sun Nov 22 14:58:37 2015  0.000000 seconds
```